

BVH TCP/IP Stream Format Description

Perception Axis supports real-time BVH format data export via TCP/IP protocol.

The default port for TCP/IP service is 7001. Once client connection detected, Perception Axis will send real-time BVH format data via TCP/IP protocol. The port can be changed in the Broadcasting tap of File-> Settings Menu.

1. Format description

A TCP/IP BVH data package including the orientation and position information of below bones:

| Bone ID | 00 | 01 | 02 | 03 | 04 | 05 | 06 | 20 | 19 | 18 | 17 | 16 | 15 | 07 | 08 | 9 | 10 | 35 | 36 | 37 | 38 |
|--------------------|----------------|----------|----------|--------------|----------|--------------|--------------|--------------|--------------|-----------|-----------|----------|----------|----------|----------|----------|----------|---------|----|----------|----------|
| Bone | one Hip | RUL | RL | RF | | LL | LF | S0 | S1 | 63 | S3 | N | н | RS | RA | RFA | RH | RH | RH | RH | RI |
| | | | | | LUL | | | | | S2 | | | | | | | | T1 | T2 | Т3 | ні |
| Sensor Id(Hex) | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | 11 | | | 10 | 08 | 09 | 0A | ОВ | | 24 | 25 | |
| Bone ID | 39 | 40 | 41 | 42 | 43 | 44 | 45 | 46 | 47 | 48 | 49 | 50 | 51 | 52 | 53 | 11 | 12 | 13 | 14 | 67 | 68 |
| Bone | RHI 1 | RHI 2 | RH I3 | RI H M | RH M1 | RH M 2 | RH M 3 | RI HR | RH R1 | RH R2 | RH R3 | RI HP | RH P1 | RH P2 | RH P3 | LS | LA | LF A | LH | LHT 1 | LH T2 |
| Sensor ID (Hex) | 27 | 28 | | | 2B | 2C | | | 2F | 30 | | | 33 | 34 | | ОС | 0D | 0E | OF | | 44 |
| Bone ID | 69 | 70 | 71 | 72 | 73 | 74 | 75 | 76 | 77 | 78 | 79 | 80 | 81 | 82 | 83 | 84 | 85 | | | | |
| Bone | LHT 3 | ЦНІ | LH I1 | LH I2 | LHI 3 | LI H M | LH M 1 | LH M 2 | LH M 3 | LI HR | LH R1 | LH R2 | LH R3 | LI HP | LH P1 | LHP 2 | LH P3 | | | | |
| Sensor ID (Hex) | 45 | | 47 | 48 | | | 4B | 4C | | | 4F | 50 | | | 53 | 54 | | | | | |

Bone and data definition:

00: Hip, root, global displacement in x, y, z (unit: cm) and global orientation in x, y, z (unit: degree)

01: **RUL** (Right Up Leg), local rotation angle relative to hip and (for BVH with displacement) local displacement relative to Hip

02: **RL** (Right Leg), local rotation angle relative to RUL and (for BVH with displacement) local displacement relative to RUL

03: **RF** (Right Foot), local rotation angle relative to RL and (for BVH with displacement) local displacement relative to RL

04: LUL (Left Up Leg), local rotation angle relative to hip and (for BVH with displacement) local

北京诺亦腾科技有限公司



displacement relative to Hip

- 05: **LL** (Left Leg), local rotation angle relative to LUL and (for BVH with displacement) local displacement relative to LUL
- 06: **LF** (Left Foot), local rotation angle relative to LL and (for BVH with displacement) local displacement relative to LL
- 20: **SO** (SpineO), local rotation angle relative to hip and (for BVH with displacement) local displacement relative to Hip
- 19: **\$1** (Spine1), local rotation angle relative to \$0 and (for BVH with displacement) local displacement relative to \$0
- 18: **S2** (Spine2), local rotation angle relative to S1 and (for BVH with displacement) local displacement relative to S1
- 17: **S3** (Spine3), local rotation angle relative to S2 and (for BVH with displacement) local displacement relative to S2
- 16: **N** (Neck), local rotation angle relative to S3 and (for BVH with displacement) local displacement relative to S3
- 15: **H** (Head), local rotation angle relative to Neck and (for BVH with displacement) local displacement relative to Neck
- 07: **RS** (Right Shoulder), local rotation angle relative to S3 and (for BVH with displacement) local displacement relative to S3
- 08: **RA** (Right Arm), local rotation angle relative to RS and (for BVH with displacement) local displacement relative to RS
- 09: **RFA** (Right Forearm), local rotation angle relative to RA and (for BVH with displacement) local displacement relative to RA
- 10: **RH** (Right Hand), local rotation angle relative to RFA and (for BVH with displacement) local displacement relative to RFA
- 35: **RHT1** (Right Hand Thumb 1), local rotation angle relative to RH and (for BVH with displacement) local displacement relative to RH
- 36: **RHT2** (Right Hand Thumb 2), local rotation angle relative to RHT1 and (for BVH with displacement) local displacement relative to RHT1
- 37: **RHT3** (Right Hand Thumb 3), local rotation angle relative to RHT2 and (for BVH with displacement) local displacement relative to RHT2
- 38: **RIHI** (Right In Hand Index), local rotation angle relative to RH and (for BVH with displacement) local displacement relative to RH
- 39: **RHI1** (Right Hand Index 1), local rotation angle relative to RIHI and (for BVH with displacement) local displacement relative to RIHI
- 40: **RHI2** (Right Hand Index 2), local rotation angle relative to RHI1 and (for BVH with displacement) local displacement relative to RHI1
- 41: **RHI3** (Right Hand Index 3), local rotation angle relative to RHI2 and (for BVH with displacement) local displacement relative to RHI2
- 42: **RIHM** (Right In Hand Middle), local rotation angle relative to RH and (for BVH with displacement) local displacement relative to RH
- 43: **RHM1** (Right Hand Middle 1), local rotation angle relative to RIHM and (for BVH with displacement) local displacement relative to RIHM



- 44: **RHM2** (Right Hand Middle 2), local rotation angle relative to RHM1 and (for BVH with displacement) local displacement relative to RHM1
- 45: **RHM3** (Right Hand Middle 3), local rotation angle relative to RHM2 and (for BVH with displacement) local displacement relative to RHM2
- 46: **RIHR** (Right In Hand Ring), local rotation angle relative to RH and (for BVH with displacement) local displacement relative to RH
- 47: **RHR1** (Right Hand Ring 1), local rotation angle relative to RIHR and (for BVH with displacement) local displacement relative to RIHR
- 48: **RHR2** (Right Hand Ring 2), local rotation angle relative to RHR1 and (for BVH with displacement) local displacement relative to RHR1
- 49: **RHR3** (Right Hand Ring 3), local rotation angle relative to RHR2 and (for BVH with displacement) local displacement relative to RHR2
- 50: **RIHP** (Right In Hand Pinky), local rotation angle relative to RH and (for BVH with displacement) local displacement relative to RH
- 51: **RHP1** (Right Hand Pinky 1), local rotation angle relative to RIHP and (for BVH with displacement) local displacement relative to RIHP
- 52: **RHP2** (Right Hand Pinky 2), local rotation angle relative to RHP1 and (for BVH with displacement) local displacement relative to RHP1
- 53: **RHP3** (Right Hand Pinky 3), local rotation angle relative to RHP2 and (for BVH with displacement) local displacement relative to RHP2
- 11: **LS** (Left Shoulder), local rotation angle relative to S3 and (for BVH with displacement) local displacement relative to S3
- 12: **LA** (Left Arm), local rotation angle relative to LS and (for BVH with displacement) local displacement relative to LS
- 13: **LFA** (Left Forearm), local rotation angle relative to LA and (for BVH with displacement) local displacement relative to LA
- 14: **LH** (Left Hand), local rotation angle relative to LFA and (for BVH with displacement) local displacement relative to LFA
- 67: **LHT1** (Left Hand Thumb 1), local rotation angle relative to LH and (for BVH with displacement) local displacement relative to LH
- 68: **LHT2** (Left Hand Thumb 2), local rotation angle relative to LHT1 and (for BVH with displacement) local displacement relative to LHT1
- 69: **LHT3** (Left Hand Thumb 3), local rotation angle relative to LHT2 and (for BVH with displacement) local displacement relative to LHT2
- 70: **LIHI** (Left In Hand Index), local rotation angle relative to LH and (for BVH with displacement) local displacement relative to LH
- 71: **LHI1** (Left Hand Index 1), local rotation angle relative to LIHI and (for BVH with displacement) local displacement relative to LIHI
- 72: **LHI2** (Left Hand Index 2), local rotation angle relative to LHI1 and (for BVH with displacement) local displacement relative to LHI1
- 73: **LHI3** (Left Hand Index 3), local rotation angle relative to LHI2 and (for BVH with displacement) local displacement relative to LHI2
- 74: LIHM (Left In Hand Middle), local rotation angle relative to LH and (for BVH with displacement) local

北京诺亦腾科技有限公司



displacement relative to LH

75: **LHM1** (Left Hand Middle 1), local rotation angle relative to LIHM and (for BVH with displacement) local displacement relative to LIHM

76: **LHM2** (Left Hand Middle 2), local rotation angle relative to LHM1 and (for BVH with displacement) local displacement relative to LHM1

77: **LHM3** (Left Hand Middle 3), local rotation angle relative to LHM2 and (for BVH with displacement) local displacement relative to LHM2

78: **LIHR** (Left In Hand Ring), local rotation angle relative to LH and (for BVH with displacement) local displacement relative to LH

79: **LHR1** (Left Hand Ring 1), local rotation angle relative to LIHR and (for BVH with displacement) local displacement relative to LIHR

80: **LHR2** (Left Hand Ring 2), local rotation angle relative to LHR1 and (for BVH with displacement) local displacement relative to LHR1

81: **LHR3** (Left Hand Ring 3), local rotation angle relative to LLR2 and (for BVH with displacement) local displacement relative to LHR2

82: **LIHP** (Left In Hand Pinky), local rotation angle relative to LH and (for BVH with displacement) local displacement relative to LH

83: **LHP1** (Left Hand Pinky 1), local rotation angle relative to LIHP and (for BVH with displacement) local displacement relative to LIHP

84: **LHP2** (Left Hand Pinky 2), local rotation angle relative to LHP1 and (for BVH with displacement) local displacement relative to LHP1

85: **LHP3** (Left Hand Pinky 3), local rotation angle relative to LHP2 and (for BVH with displacement) local displacement relative to LHP2

It is noted that all bone data, except for the hip, are local data defined in parent bone coordinate.

Sample data:

| Hips Position | Hips Rotation | RightUpLeg RotationhtLeg Rotat | RightFoot Rotation | LeftUpLeg Rotation | eftLeg Rotatio | LeftFoot Rotation | etc. | |
|---------------------|-------------------|--------------------------------|---------------------|--------------------|----------------|--------------------|---------|---------------|
| X Y Z | Y X | Z Y X Z Y X Z | Y X Z | Y X Z | Y X Z | Y X Z | etc. | |
| 43.62 102.72 151.18 | -9.5 -0.47 -0.0 | 04 -6.9 -9.88 8.52 0 29.14 0 | -21.75 -19.81 -1.86 | 22.59 -26.08 -6.62 | 0 43.91 0 | 19.84 -9.06 -8.4 | 2.71 2. | .66 0.64 0.7 |
| 43.67 102.61 151.28 | -11.3 -0.47 -0.3 | 38 -6.2 -9.99 8.79 0 29.41 0 | -20.74 -19.9 -2.23 | 24.92 -27.55 -6 | 0 46.75 0 | 18.49 -8.83 -9.23 | 3.7 2. | .66 0.83 0.9 |
| 43.72 102.5 151.38 | -11.78 -0.46 -0.4 | 47 -6.15 -10.14 8.82 0 29.83 0 | -20.37 -20.16 -2.23 | 25.7 -28.85 -5.66 | 0 49.09 0 | 17.39 -8.36 -9.79 | 2.93 2. | .62 0.88 0.7 |
| 43.83 102.41 151.54 | -13.73 -0.36 -0.8 | 81 +5.38 -10.33 9.05 0 30.07 0 | -19.3 -20.25 -2.53 | 27.77 -30.3 -5.06 | 0 51.47 0 | 16.14 -8.31 -10 | 4.02 2. | . 53 1. 11 1 |
| 43.95 102.32 151.69 | -14.23 -0.35 -0.8 | 89 +5.23 -10.49 9.03 0 30.5 0 | -19 -20.48 -2.43 | 28.08 -31.53 -4.71 | 0 53.22 0 | 15.35 -8.05 -9.62 | 3.01 2. | .42 1.18 0.8 |
| 44.11 102.23 151.82 | -16.25 -0.37 -1.1 | 13 -4.34 -10.7 9.11 0 30.88 0 | -17.93 -20.55 -2.59 | 29.54 -32.77 -3.85 | 0 54.73 0 | 15.23 -8.58 -9.54 | 4.06 2 | 2.4 1.31 1 |
| 44.28 102.15 151.95 | -16.75 -0.39 -1.1 | 17 -4.2 -10.87 9.01 0 31.33 0 | -17.57 -20.75 -2.5 | 29.39 -33.84 -3.2 | 0 55.57 0 | 15.33 -8.87 -9.07 | 2.75 2. | .26 1.39 0.7 |
| 44.44 102.08 152.1 | -18.7 -0.57 -1.2 | 22 -3.42 -10.99 8.89 0 31.85 0 | -16.43 -20.86 -2.65 | 30.33 -34.54 -2.14 | 0 55.97 0 | 15.25 -9.17 -8.62 | 3.73 2. | .34 1.43 0.9 |
| 44.59 102.01 152.28 | -19.19 -0.61 -1.2 | 21 +3.28 -11.11 8.74 0 32.29 0 | -16.1 -21.07 -2.54 | 29.83 -35.25 -1.19 | 0 55.84 0 | 14.96 -9.47 -8.06 | 4.22 2. | . 38 1.42 1.1 |
| 44.73 101.93 152.46 | -21.01 -0.93 -1.1 | 12 +2.67 -11.09 8.45 0 32.87 0 | -14.84 -21.25 -2.71 | 30.27 -35.43 0.16 | 0 55.26 0 | 14.49 -9.95 -7.7 | 5.12 2. | .56 1.39 1.3 |
| 44.86 101.86 152.64 | -21.5 -1 -1.0 | 08 +2.49 -11.17 8.28 0 33.27 0 | -14.49 -21.46 -2.63 | 29.41 -35.81 1.37 | 0 54.26 0 | 13.78 -10.31 -7.15 | 5.6 2. | 62 1.36 1.4 |
| 44.99 101.79 152.83 | -23.47 -1.25 -0.9 | 92 -1.72 -11.26 7.93 0 33.88 0 | -13.21 -21.64 -2.89 | 29.56 -35.75 2.89 | 0 52.91 0 | 13.2 -10.7 -6.93 | 6.59 2. | .76 1.3 1.7 |
| 45.14 101.72 153.01 | -23.97 -1.31 -0.8 | 87 -1.59 -11.35 7.74 0 34.29 0 | -12.84 -21.85 -2.86 | 28.22 -35.88 4.34 | 0 51.23 0 | 12.62 -10.91 -6.7 | 5.16 2. | .66 1.39 1.3 |
| 45.3 101.64 153.23 | -26 -1.46 -0.7 | 73 +0.86 -11.57 7.38 0 34.98 0 | -11.47 -22.09 -3.21 | 27.71 -35.58 6.1 | 0 49.25 0 | 12.49 -11.04 -6.84 | 6.17 2. | 74 1.34 1.6 |
| 45.46 101.56 153.41 | -23.97 -1.31 -0.8 | 87 -3.22 -11.42 7.31 0 35.16 0 | -11.12 -22.49 -3.18 | 23.33 -35.76 7.66 | 0 46.85 0 | 12.17 -10.41 -6.48 | 3.21 2. | .54 1.57 0.8 |
| 45.65 101.46 153.63 | -26 -1.46 -0.7 | 73 -2.48 -11.67 6.94 0 35.86 0 | -9.84 -22.73 -3.58 | 22.56 -35.08 9.48 | 0 44.47 0 | 12.22 -9.83 -6.7 | 4.23 2. | 64 1.51 1.1 |
| 45.83 101.36 153.85 | -26.51 -1.49 -0. | .7 -2.31 -11.85 6.74 0 36.39 0 | -9.49 -23.02 -3.57 | 20.82 -34.52 11.1 | 0 41.9 0 | 11.74 -8.86 -6.67 | 2.79 2. | .58 1.67 0.7 |
| 46.01 101.23 154.13 | -28.59 -1.63 -0.6 | 63 +1.36 -12.09 6.45 0 37.08 0 | -8.35 -23.33 -3.92 | 20.2 -33.54 12.86 | 0 39.46 0 | 11.79 -7.97 -7.08 | 3.84 2. | .66 1.67 1 |




2. Bone map and coordinate system

BVH coordinate definition:


Displacement is defined in local coordinate system of parent body segment, for hip (root): X -> north, Y -> up, Z -> east

Angle sequence is configurable, with default sequence YXZ, and defined in local coordinate system of parent body segment




17 Sensors map





Initial bone pose is T-pose, with x->left, y->up, z->forward, as shown figure below:





Initial bone pose



3. Attached: BVH head file (without displacement)

```
HIERARCHY
ROOT Hips
    OFFSET 0.000000 104.194260 0.000000
    CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
    JOINT RightUpLeg
    {
         OFFSET -11.500000 0.000000 0.000000
         CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
         JOINT RightLeg
         {
              OFFSET 0.000000 -48.000000 0.000000
              CHANNELS 6 Xposition Yposition Zposition Yrotation Zrotation
             JOINT RightFoot
             {
                  OFFSET 0.000000 -48.000000 0.000000
                  CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                  End Site
                  {
                       OFFSET 0.000000 -1.806452 18.064516
                  }
             }
         }
    }
    JOINT LeftUpLeg
         OFFSET 11.500000 0.000000 0.000000
         CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
         JOINT LeftLeg
         {
              OFFSET 0.000000 -48.000000 0.000000
             CHANNELS 6 Xposition Yposition Zposition Yrotation Zrotation
             JOINT LeftFoot
             {
                  OFFSET 0.000000 -48.000000 0.000000
                  CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                  End Site
                  {
```



```
OFFSET 0.000000 -1.806452 18.064516
                 }
             }
        }
    }
    JOINT Spine
         OFFSET 0.000000 13.878078 0.000000
         CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
         JOINT Spine1
         {
             OFFSET 0.000000 11.312473 0.000000
             CHANNELS 6 Xposition Yposition Zposition Yrotation Zrotation
             JOINT Spine2
             {
                  OFFSET 0.000000 11.779724 0.000000
                  CHANNELS 6 Xposition Yposition Zposition Yrotation Zrotation
                  JOINT Spine3
                  {
                      OFFSET 0.000000 11.312473 0.000000
                      CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                       JOINT Neck
                      {
                           OFFSET 0.000000 12.091224 0.000000
                           CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                           JOINT Head
                           {
                               OFFSET 0.000000 9.000000 0.000000
                               CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                               End Site
                               {
                                    OFFSET 0.000000 18.000000 0.000000
                               }
                           }
                      }
                      JOINT RightShoulder
                       {
                           OFFSET -3.500000 8.060816 0.000000
                           CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                           JOINT RightArm
                           {
```

OFFSET -17.500000 0.000000 0.000000



```
CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                                JOINT RightForeArm
                                {
                                    OFFSET -29.000000 0.000000 0.000000
                                    CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                                    JOINT RightHand
                                      OFFSET -28.000000 0.000000 0.000000
                                      CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                                      JOINT RightHandThumb1
                                      {
                                           OFFSET -2.702960 0.206400 3.388480
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT RightHandThumb2
                                                OFFSET -2.746160 -0.644800 2.834744
                                                CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                                JOINT RightHandThumb3
                                                {
                                                    OFFSET -2.126080 -0.808800 1.594552
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                      End Site
                                                    {
                                                         OFFSET -1.800000 -0.900000 1.800000
                                                    }
                                               }
                                           }
                                      JOINT RightInHandIndex
                                           OFFSET -3.500240 0.552000 2.148272
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT RightHandIndex1
                                           {
                                                OFFSET -5.669520 -0.099200 1.085176
                                                CHANNELS 6 Xposition Yposition Zposition Yrotation
```



Xrotation Zrotation

```
JOINT RightHandIndex2
                                               {
                                                    OFFSET -3.919920 -0.191200 0.199320
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT RightHandIndex3
                                                    {
                                                         OFFSET -2.222000 -0.138400 -0.082208
                                                         CHANNELS 6
                                                                          Xposition
                                                                                       Yposition
Zposition Yrotation Xrotation Zrotation
                                                        End Site
                                                        {
                                                                        -2.280000
                                                                                       0.000000
                                                             OFFSET
0.000000
                                                        }
                                                    }
                                               }
                                           }
                                      }
                                      JOINT RightInHandMiddle
                                      {
                                           OFFSET -3.673840 0.561600 0.822346
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT RightHandMiddle1
                                           {
                                               OFFSET -5.618239 -0.091200 0.341108
                                               CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                               JOINT RightHandMiddle2
                                               {
                                                    OFFSET -4.273920 -0.291200 -0.200651
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT RightHandMiddle3
                                                    {
                                                         OFFSET -2.668640 -0.207200 -0.240782
                                                        CHANNELS 6
                                                                          Xposition
                                                                                       Yposition
Zposition Yrotation Xrotation Zrotation
                                                        End Site
                                                        {
                                                                        -2.280000
                                                                                       0.000000
                                                             OFFSET
```



0.000000

```
}
                                                    }
                                                }
                                           }
                                      JOINT RightInHandRing
                                      {
                                           OFFSET -3.653760 0.588000 -0.140000
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT RightHandRing1
                                                OFFSET -5.000000 -0.024000 -0.521600
                                                CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                                JOINT RightHandRing2
                                                {
                                                    OFFSET -3.652000 -0.285600 -0.742400
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT RightHandRing3
                                                         OFFSET -2.548000 -0.186400 -0.441600
                                                         CHANNELS
                                                                      6
                                                                           Xposition
                                                                                        Yposition
Zposition Yrotation Xrotation Zrotation
                                                         End Site
                                                              OFFSET
                                                                         -2.160000
                                                                                       0.000000
0.000000
                                                         }
                                                    }
                                                }
                                           }
                                      JOINT RightInHandPinky
                                           OFFSET -3.432800 0.509600 -1.304800
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT RightHandPinky1
                                                OFFSET -4.494400 -0.024000 -1.176000
```



```
CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                                JOINT RightHandPinky2
                                                {
                                                     OFFSET -2.848800 -0.164000 -0.904000
                                                     CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                     JOINT RightHandPinky3
                                                         OFFSET -1.765600 -0.142400 -0.662400
                                                         CHANNELS
                                                                            Xposition
                                                                                        Yposition
Zposition Yrotation Xrotation Zrotation
                                                         End Site
                                                         {
                                                              OFFSET
                                                                          -1.680000
                                                                                        0.000000
0.000000
                                                         }
                                                    }
                                                }
                                           }
                                       }
                                     }
                                }
                           }
                       JOINT LeftShoulder
                           OFFSET 3.500000 8.060816 0.000000
                           CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation Zrotation
                           JOINT LeftArm
                           {
                                OFFSET 17.500000 0.000000 0.000000
                                CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                                JOINT LeftForeArm
                                     OFFSET 29.000000 0.000000 0.000000
                                     CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
Zrotation
                                     JOINT LeftHand
                                     {
                                       OFFSET 28.000000 0.000000 0.000000
                                       CHANNELS 6 Xposition Yposition Zposition Yrotation Xrotation
```



Zrotation

```
JOINT LeftHandThumb1
                                           OFFSET 2.702960 0.206400 3.388480
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT LeftHandThumb2
                                           {
                                               OFFSET 2.746160 -0.644800 2.834744
                                               CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                               JOINT LeftHandThumb3
                                                    OFFSET 2.126080 -0.808800 1.594552
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    End Site
                                                        OFFSET 1.800000 -0.900000 1.800000
                                               }
                                           }
                                      }
                                      JOINT LeftInHandIndex
                                      {
                                           OFFSET 3.500000 0.552000 2.148000
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT LeftHandIndex1
                                               OFFSET 5.668800 -0.099200 1.084800
                                               CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                               JOINT LeftHandIndex2
                                               {
                                                    OFFSET 3.920000 -0.191200 0.199200
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT LeftHandIndex3
                                                        OFFSET 2.221600 -0.138400 -0.082400
                                                                                       Yposition
                                                        CHANNELS 6 Xposition
Zposition Yrotation Xrotation Zrotation
```



```
End Site
                                                             OFFSET
                                                                         2.280000
                                                                                       0.000000
0.000000
                                                        }
                                                    }
                                               }
                                           }
                                      JOINT LeftInHandMiddle
                                           OFFSET 3.673600 0.561600 0.822320
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT LeftHandMiddle1
                                           {
                                               OFFSET 5.617840 -0.091200 0.340800
                                               CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                               JOINT LeftHandMiddle2
                                               {
                                                    OFFSET 4.273600 -0.291200 -0.200800
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT LeftHandMiddle3
                                                        OFFSET 2.668800 -0.207200 -0.240800
                                                        CHANNELS
                                                                          Xposition
                                                                                       Yposition
                                                                      6
Zposition Yrotation Xrotation Zrotation
                                                        End Site
                                                        {
                                                             OFFSET
                                                                         2.280000
                                                                                       0.000000
0.000000
                                                        }
                                                    }
                                               }
                                           }
                                      JOINT LeftInHandRing
                                           OFFSET 3.653760 0.588000 -0.140000
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
```

Xrotation Zrotation



```
JOINT LeftHandRing1
                                                OFFSET 5.000000 -0.024000 -0.521600
                                                CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                                JOINT LeftHandRing2
                                                {
                                                    OFFSET 3.652000 -0.285600 -0.742400
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT LeftHandRing3
                                                    {
                                                         OFFSET 2.548000 -0.186400 -0.441600
                                                         CHANNELS
                                                                           Xposition
                                                                                       Yposition
Zposition Yrotation Xrotation Zrotation
                                                         End Site
                                                         {
                                                              OFFSET
                                                                         2.160000
                                                                                       0.000000
0.000000
                                                         }
                                                    }
                                                }
                                           }
                                      JOINT LeftInHandPinky
                                           OFFSET 3.432800 0.509600 -1.304800
                                           CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                           JOINT LeftHandPinky1
                                           {
                                                OFFSET 4.494400 -0.024000 -1.176000
                                                CHANNELS 6 Xposition Yposition Zposition Yrotation
Xrotation Zrotation
                                                JOINT LeftHandPinky2
                                                     OFFSET 2.848800 -0.164000 -0.904000
                                                    CHANNELS 6 Xposition Yposition Zposition
Yrotation Xrotation Zrotation
                                                    JOINT LeftHandPinky3
                                                         OFFSET 1.765600 -0.142400 -0.662400
                                                         CHANNELS 6
                                                                           Xposition
                                                                                       Yposition
```



Zposition Yrotation Xrotation Zrotation

```
End Site
                                                      {
                                                                                  0.000000
                                                          OFFSET
                                                                      1.680000
0.000000
                                                      }
                                                 }
                                             }
                                         }
                                    }
                                  }
                              }
                         }
                     }
                 }
            }
        }
    }
}
```

北京诺亦腾科技有限公司



4. Revision history

| Revision | Author | date | Description/changes |
|----------|--------------|------------|-----------------------|
| D1 | He Yuanhui | 7/1/2013 | Initial released |
| D2 | He Yuanhui | 1/6/2014 | Added: |
| | | | |
| | | | Modified: |
| | | | Data format desc. |
| D3 | He Yuanhui | 6/24/2014 | Added: |
| | | | |
| | | | Modified: |
| | | | Default service port. |
| D4 | He Yuanhui | 11/25/2014 | Added: |
| | | | Add fingers data |
| | | | Modified: |
| | | | |
| D5 | Chen Jinzhou | 12/25/2014 | Modified: |
| | | | |
| D6 | He Yuanhui | 1/21/2015 | Modified: |
| | | | Data sample chart |